

## VI.6.3-PPDUTIL-RRSFREE PROGRAM PPDUTIL COMMAND RRSFREE

### Purpose

Command RRSFREE analyzes the RRS primary and free pool files in the Preprocessor Data Base and prints the following information:

- o the number of RRS stations that have free pool chains
- o the number of free pool records currently belonging to chains
- o a list of all the RRS stations that have free pool chains and the record numbers of the free pool records that make up those chains

Warning messages are printed if:

- o any free pool chain ends with a record marked not active
- o any free pool records marked as in use do not belong to free pool chains
- o any free pool records belong to more than one chain

These problems can arise if a job is terminated abnormally or while writing RRS data or if multiple jobs attempt to update freepool records at the same time.

### Input Data

<u>Card</u>	<u>Field</u>	<u>Format</u>	<u>Contents</u>
1	1		'@RRSFREE'
	2		'RLSE' <u>1</u> /
	3		'DETAIL' <u>2</u> /

Notes:

- 1/ Field is optional. If specified any free pool records marked in use but not part of a chain will be released.
- 2/ Field is optional. If specified a listing of all freepool chains will be printed.