

## IX.3.0B-SYSTEM-UFLDST SUBROUTINE UFLDST

### Description

Subroutine UFLDST prints error messages for subroutine UFIELD [[Hyperlink](#)].

### Calling Sequence

CALL UFLDST (NFLD, ISTRT, LENGTH, ITYPE, NREP, INTEGR, REAL, LCHAR, CHAR, LLPAR, LRPAR, LASK, LATSGN, LAMPS, LEQUAL, ISTAT, NUMERR, NUMWRN)

### Argument List

<u>Argument</u>	<u>Input/ Output</u>	<u>Type</u>	<u>Dimension</u>	<u>Description</u>
NFLD	Input	I*4	1	See note <a href="#">1</a> /
ISTRT	Input	I*4	1	See note <a href="#">1</a> /
LENGTH	Input	I*4	1	See note <a href="#">1</a> /
ITYPE	Input	I*4	1	See note <a href="#">1</a> /
NREP	Input	I*4	1	See note <a href="#">1</a> /
INTEGR	Input	I*4	1	See note <a href="#">1</a> /
REAL	Input	I*4	1	See note <a href="#">1</a> /
LCHAR	Input	I*4	1	See note <a href="#">1</a> /
CHAR	Input	A4	LCHAR	See note <a href="#">1</a> /
LLPAR	Input	I*4	1	See note <a href="#">1</a> /
LRPAR	Input	I*4	1	See note <a href="#">1</a> /
LASK	Input	I*4	1	See note <a href="#">1</a> /
LATSGN	Input	I*4	1	See note <a href="#">1</a> /
LAMPS	Input	I*4	1	See note <a href="#">1</a> /
LEQUAL	Input	I*4	1	See note <a href="#">1</a> /
ISTAT	Input	I*4	1	See note <a href="#">1</a> /
NUMERR	Both	I*4	1	See note <a href="#">2</a> /

<u>Argument</u>	<u>Input/ Output</u>	<u>Type</u>	<u>Dimension</u>	<u>Description</u>
NUMWRN	Both	I*4	1	See note <u>3</u> /

Notes:

1/ See Section IX.3.OB-UFIELD [[Hyperlink](#)].

2/ Number of times subroutine UEROR [[Hyperlink](#)] has been called.

3/ Number of times subroutine UWARN [[Hyperlink](#)] has been called.