

Purpose

Command SETGDFLT sets defaults for a Global Function, Procedure or Technique.

Format

@SETGDFLT

<p><u>FUNCTION</u> [NAME=]funcname [<u>PASSWORD</u>=]password</p> <p style="text-align: center;">or</p> <p><u>PROCEDURE</u> [NAME=]procname [<u>PASSWORD</u>=]password parmname=value1</p> <p style="text-align: center;">or</p> <p><u>TECHNIQUE</u> [NAME=]techname2 [<u>PASSWORD</u>=]password { [argname=]value2 }</p>	<p style="font-size: 2em;">{</p> <table border="0" style="border-collapse: collapse;"> <tr> <td style="padding: 0 5px;">techname1</td> <td style="font-size: 2em;">}</td> </tr> </table>	techname1	}
techname1	}		

Parameter Description

<u>Parameter</u>	<u>Required/ Optional</u>	<u>Maximum Characters</u>	<u>Description</u>
funcname	R	8	Name of Function for which Techniques are to defaulted <u>1</u> /
password	R	4	Password; must be the same as the password specified when the Global HCL files were created using program FILECRAT
techname1	R	8	Name of Technique to be defaulted
(Y°) (N) (int)	0	1	Default for using the Technique where: Y = YES = ON N = NO = OFF int = any integer (default must be enclosed in parenthesis and must follow the Technique name with no spaces)
procname	R	8	Name of the Procedure for which parameters are to be defaulted

<u>Parameter</u>	<u>Required/ Optional</u>	<u>Maximum Characters</u>	<u>Description</u>
parmname	O	8	Name of the parameter to be defaulted
value1	R		Defaulted value for the parameter
techname2			Name of the Technique for which Arguments are to be defaulted <u>1/</u>
argname	O	8	Name of the Argument to be defaulted
value2	R		Defaulted value for the Argument

Notes:

1/ Each Function for which Techniques are to be defaulted MUST begin on a new card. Each Technique for which Arguments are to be defaulted must begin on a new card. Each Procedure for which parameters are to be defaulted must begin on a new card.

Examples

The following example sets the default for the Global Technique MDR. An Argument called TABLE is given a default of 1 using the password OFS.

```
@SETGDFLT TECHNIQUE NAME=MDR PASSWORD=OFS TABLE=1
```