VI.5.3D-SYSTEM-PRTMDR6 PROGRAM FCST HCL TECHNIQUE PRTMDR6

Purpose

Technique PRTMDR6 sets whether a table will be printed comparing MDR derived precipitation and observed precipitation at stations where both are available.

The comparison is only made at stations with 6 hour summations of precipitation.

Valid values are NO (0) and YES (1).

The Global default is NO (0).

This Technique is Universal.

Form of Input

PRTMDR6(integer)

where integer is 0 or 1 specifying whether PRTMDR6 is off or on

Example

PRTMDR6(1)

A table comparing MDR-derived precipitation and observed precipitation will be printed.