IX.3.3B-SYSTEM-RDLIST SUBROUTINE RDLIST

Description

Subroutine RDLIST reads a list of character strings using the following free format rules:

- 1. values must be separated by at least one blank
- 2. if an '*' is encountered then decoding on the current card stops and the next card is read as a continuation.

Only the first 72 columns of the card are read.

Calling Sequence

CALL RDLIST (ICARDS, NCARDS, ICARD, LIST, NLIST, NWORDS, NUMC, IERR)

Argument List

Argument	Input/ <u>Output</u>	Type	Dimension	Description
ICARDS	Input	I*4	1	Number of current card in group of input cards
NCARDS	Input	I*4	1	Total number of cards in input card group
ICARD	Input	A80	NCARDS	Array of input cards
LIST	Output	A4	(5,100)	Array of list items
NLIST	Output	I*4	1	Number of items in array LIST
NWORDS	Input	I*4	1	Number of words allowed in each list item
NUMC	Output	I*4	100	Number of characters in each item in array LIST
IERR	Output	I*4	1	Error indicator: O = no errors 1 = error encountered